#REVISION HISTORY#

- Setup version 6.0.0 released 17.11.2021
- Fixed issue with Microsoft access database drivers crashing after Windows update.
- Setup version 5.9.4 released 03.12.2021
- Fixed bug with hidden card ID tab in function cards.
- Setup version 5.9.1 released 03.11.2021
- Added support for Generation 2 readers configuration, and firmware upgrade.
- Added new firmware 2.03 for CNV1000 TCP converter with auto restart.
- Fixed missing pictures in readers help window.
- Added option in View menu to save/load and set default filter of the live events grid.
- Fixed bug in Web report All users report crash.
- Added support for Uniview video systems.
- Setup version 5.7.1 released 29.12.2020
- > Fixed bug in Web report
- Crystal report is distributed with setup
- Setup version 5.7.0 released 10.09.2020
- Added support for Uniview video systems
- Setup version 5.6.0 released 24.12.2019
- Added option to show user image in event grid
- Added user image in access scenarios popup message
- Fixed bug in server setup, data ports text boxes was swapped
- Setup version 5.5.1 released 08.10.2019
- Fixed bug with generating access report by task
- > Fixed bug with sending mails by task
- Setup version 5.5.0 released 26.09.2019

- Added support for Dahua video system
- Moved to .NET 4.7 (Windows XP, Vista, Server 2003, Server 2008 are no longer supported)
- Fixed bug with Maps creation and element display

Setup version 5.4.0 released 14.08.2019

- Fixed bug when event column cannot be restored once it is manually hidden
- Added PIN length setting for biometry readers with keypad, used for T&A codes selection

Setup version 5.2.5 released 31.07.2019

Fixed bug with Reset rolling code button in Users window

Setup version 5.2.4 released 07.07.2019

Increased beacon timeout from Server to Client from 30 to 120 seconds. Long server operations were causing Client to disconnect from server.

Setup version 5.2.3 released 05.07.2019

- Added option to check for software update under Help menu
- Fixed bug with events translation
- Fixed installation of the Web server on the systems without .NET 2.0 installed
- Fixed installation of Crystal reports

Setup version 5.2.2 released 07.06.2019

- Fixed bug in Reader properties form in Spanish language
- Removed multi-instances of the Client in the same PC

Setup version 5.2.1 released 30.05.2019

- Fixed bug with saving custom reports
- Added rolling code receiver support
- Added display unit support
- Added controller counter support
- Added option in Users report Authorizations per door
- More instances of the Client can run simultaneously in the same PC connected to different Servers
- Crystal report engine upgraded from 13.0.20 to 13.0.35
- Added option for database backup and restore
- Added option for manual deletion of old evens log
- Added option for licensing by file instead of USB dongle
- Access events are sent to NxWitness and DigitalWatchdog video systems
- Added summary of Users distinct count and total access events in the Access report

- Modified Client-Server connecting procedure. Connecting with Operator already connected from other Client will cause termination of the previous connection.
- Added Controller firmware 4.18 with support for Rolling code receiver, Display unit and Counter

Setup version 5.0.4 released 27.10.2018

- > Fixed bug in changing operator password
- Added support for vehicle license plate recognition camera with 26 bit Wiegand output and plate number conversion using SHA-1

Setup version 5.0.1 released 13.09.2018

- Added licensing model with free and full version
- Added support for NxWitness and DigitalWatchdog video systems
- Removed requirement for USB dongle for remote PC connection
- Changed live events grid

Setup version 4.6.3 released 21.12.2017

- Added missing translations of the user interface
- Added selectable delays in Search portals feature
- Updated icons in some menus

Setup version 4.6.2 released 07.12.2017

- Added toolbar with buttons for Users setup, Reports and Display
- Added customizable toolbars at the left, right and bottom side of the main display with drag/drop feature from hardware panel and "Run scenarios" menu
- Added Controller firmware ver. 4.3 with minor fix in time zone duration

Setup version 4.5.2 released 24.08.2017

- Added Holiday ranges
- Added Controller firmware with support for Holiday ranges ver. 4.2

Setup version 4.5.1 released 26.07.2017

- Fixed bug in T&A calculation with SQL database from version 4.5
- Fixed bug with database upgrade of SQL in version 4.3. Client report error with controller properties window.
- Added Controller firmware with support for lift control ver. 4.1

Setup version 4.5.0 released 07.04.2017

- Added Master Shift report in T&A reports
- Fixed bug in T&A calculation in some conditions break time was not calculated
- Redesigned Access level configuration window
- Fixed bug If logged operator at client is with some of the doors or controllers hidden, for some events will get in the event window error message
- Updated German translation
- T&A reports window is redesigned
- Added Lift control
- Changed default state of controller door sensors to "disabled"
- Added Wiegand "Connect W26" for support of Connect remotes receiver
- Added Wiegand "Connect SN W26" for support of Connect SN remotes receiver
- Bug fixed some controller error events are displayed with number instead text
- Added Controller firmware with support for lift control ver. 4.0

Setup version 4.3.4 released 06.02.2017

- Improved Access database auto repair
- Added Wiegand 24
- Added Wiegand 32
- > Added in scenarios option to send mail to user that trigger the access event

Setup version 4.3.3 released 21.02.2017

- Added filters and additional setting in Muster report
- Fixed name of the SQL database to "NSistem"
- > Added JCM Radio receiver "Connect" as reader model
- Added 4 readers wiegand protocols for JCM Connect receiver
- Updated German manual
- Updated Czech GUI

Setup version 4.3.2 released 27.01.2017

Fixed Input and Output states info display when Client connect to Server

Setup version 4.3.1 released 11.01.2017

- Added quick help buttons on windows
- Fixed bug with user output activation settings
- Added server log files for diagnostics
- Added automatic Access database repair
- Added scenarios
- Added Access events details display
- Added Controller firmware with support for additional output commands ver. 3.3

- Setup version 1.3.0 released 18.09.2016
 - Client version = 4.2.0.0
 - Server version = 4.2.0.0
- Added Global Anti pass back
- Added keypad backlight control for B100PAD and BIOPAD
- Added firmware updates:
 - B100 biometry range B100Net v1.9
 - BIOC3 biometry range BioC3_v1.26
- Setup version 1.2.0 released 18.05.2016
 - Client version = 4.1.0.0
 - Server version = 4.1.0.0
- Added Muster report
- Added ID card designer and printing
- Changed icons for desktop readers
- Fixed bug when adding new user name field and outputs was not cleared
- Fixed bug on change of PIN length some of the readers was not updated
- Fixed bug removed function cards from T&A user selection grid
- Setup version 1.1.43 Released 30.01.2016
 - Client version = 4.0.6.0
 - Server version = 4.0.6.0
- Added Global Fire option
- Added "Add Controller" in Search devices
- Added "Copy ID" for readers in Search devices
- Changed reader default value "Access by Time zones" to false
- Added users filter in users window
- Added option to rename Detail1-Detail5 in users window
- > Fixed bug with fingerprint enrolment timeout
- > 0
- Added CNV1000 firmware with improved RS485 communication Ver 2.2
- Setup version 1.1.42 Released 10.12.2015
 - Client version = 4.0.5.0
 - Server version = 4.0.5.0
 - Added disclaimer in evacuation report

- Fixed bug -communication with hardware stopped if system time changed to previous time
- Fixed bug after Windows resume from sleep, Server may be no responsive
- Added option in system parameters/USB desktop reader to select convert from 7 to 4 bytes for Desfire cards
- Added start/stop time validity for users. If used, Access controller firmware must be upgraded to version 2.73 or higher
- Added count of users in areas in Evacuation report
- Added copy/paste/save image to file right click menu on user image
- Added Access controller firmware file version 2.73 for support of start/stop validity time
- Added Access controller network firmware version 2.1 with support for NO-IP DNS server

Setup version 1.1.41

- Client version = 4.0.4.1
- Server version = 4.0.4.0
- Added pending updates count and connected clients count in status bar of Main window
- Fixed bug possible database problem when PC going to sleep mode

Setup version 1.1.39

- Client version = 4.0.3.3
- Server version = 4.0.3.3
- Added New USB Desktop readers
- Added save to file evacuation report
- Added sort by name (Portals, controllers, access levels..... and other)
- Added USB Desktop readers default card type in system parameters and in users window
- Changes in web camera handling
- Fixed In "Settings -> Servers", if changing server name and this server was the default, then it was removed from default server and default server was set to "None"

- Setup version 1.1.37
 - Client version = 4.0.2.1
 - Server version = 4.0.2.2
 - Added Authorizations report
 - Changed ID list report is generated from a separate window with user selection, together with the Authorizations report
 - Added Start/Stop pulling portal
 - Added capturing user picture from installed camera
 - Improved management of pending updates (in case when there are offline readers)
 - Fixed bug from version 1.1.34 if wrong access code was entered on a keypad, in the corresponding event (access denied-bad access code) a user name was shown
 - Fixed bug Controller offline event sometimes was raising an exception event in Client
- Setup version 1.1.34
 - Client version = 4.0.0.0
 - Server version = 4.0.0.0

IMPORTANT!!!

- Client 4.0.0.0 is not compatible with previous versions of Server (ver. 3.x.x.x, 2.x.x.x...)
- Server 4.0.0.0 is not compatible with previous versions of Client (ver. 3.x.x.x, 2.x.x.x...)
- Added multiple IDs per user (default ID + 3 new additional IDs)
- Added ID type
- Added New fields for new IDs in the Import feature
- Modified in the ID report new IDs are shown (ID1, ID2, ID3) if they are not 0
- Setup version 1.1.33
 - Client version = 3.0.1.0
 - Server version = 3.0.1.0

IMPORTANT!!!

- Client 3.0.1.0 is not compatible with previous versions of Server (ver. 2.x.x.x or 1.x.x.x)

Server 3.0.1.0 is not compatible with previous versions of Client (ver. 2.x.x.x or 1.x.x.x)

- Added Use users shadow table in system parameters (option for third party software to manage users in PROS CS through PROS CS SQL database – Access database is not supported)
- Added FOC mode (Finger On Card) in system parameters
- Added Delete all users fingers in system parameters
- Added Read card details from USB desktop reader in Users window
- Added Format card on USB desktop reader
- Added showing message for duplicate name when saving user
- Added new icons for Doors, Inputs and Outputs
- Added new events for door state, lock state and alarm state (EWS firmware update needed to version 2.68 or above)
- Added EWS new firmware version 2.68
- Fixed bug with French SQL Server date format
- Fixed bug Delete all key codes was blocking the server
- Fixed bug with Absences report no report was showing if 2 months were selected and running on SQL database
- Fixed bug T&A function cards Official return and Private return were not displayed after adding to the system
- Fixed bug In firmware update window, if clicked on Upload without selecting firmware an error message was shown

Setup version 1.1.26

- Client version = 2.0.8.0
- Server version = 2.0.8.0
- Added Company details in report's footer (can be set in Settings->System parameters)
- Changed Function cards icon is bellow Operators icon instead of Users icon

Setup version 1.1.25

- Client version = 2.0.7.0
- Server version = 2.0.7.0
- Added Import from Excel (Users, Departments...)
- Added Refresh button in "Pending updates" window
- Added Language text and language flag in main menu are changing according to current language

 Fixed bug – In "Manual punch", Get events button didn't work if the software was running with SQL database

Setup version 1.1.23

- Client version = 2.0.5.0
- Server version = 2.0.6.0
- Fixed bug After adding a new controller with biometry reader in the software, reloading users on the new biometry reader or enrolling a new finger to an existing user was blocking Pending Updates (upload user to controller or biometry reader) until server restart (or PC restart)

Setup version 1.1.22

- Client version = 2.0.5.0
- Server version = 2.0.5.0
- Added Text log for Users (tab Text Log in users window)
- Fixed bug with DST (Daylight Saving Time) for time zones that currently don't have DST, but had DST in the past.
- Fixed bug Some new biometry readers were not showing in Biometry tab in Users window.

Setup version 1.1.21

- Client version = 2.0.4.0
- Server version = 2.0.4.0
- Fixed bug when changing Key length in system parameters, Biometry with keypad were not configuring automatically

Setup version 1.1.20

- Client version = 2.0.3.0
- Server version = 2.0.3.0
- Fixed bug When adding new controller with biometry reader in the software, reloading users on the new biometry reader was blocking the Pending Updates and server restart was needed
- Added Public Holiday marking in the Master report
- Added Days counting in the Summary report header (Saturdays, Sundays, Holidays...)
- Fixed bug In the Web reports, after changing the language, report data was still in the default language

Setup version 1.1.19

- Client version = 2.0.2.0
- Server version = 2.0.2.0
- Client is changed to be single instance application
- Fixed bug Summary report generated by department
- Added button "Renew access" for single entry user in users window

Setup version 1.1.18

- Client version = 2.0.1.0
- Server version = 2.0.0.1

IMPORTANT!!!

- Client 2.0.1.0 is not compatible with previous versions of Server (versions 1.x.x.x)
- Server 2.0.0.1 is not compatible with previous versions of Client (versions 1.x.x.x)
- Added feature Maps (drag and drop doors, readers, inputs and outputs to the map to have better visual surveillance)
- Added large picture from the Reader, short manual and link to the reader webpage in reader properties

- Setup version 1.1.14
 - o Client version = 1.1.5.0
 - Server version = 1.1.3.0

Added features for reducing network traffic. (Suitable for 3G networks)

- start/stop of hardware communication (in main menu)
- pulling cycle period (in "Settings->System parameters")
- Setup version 1.1.11
 - Client version = 1.1.2.0
 - Server version = 1.1.1.0
- Added feature search by ID in Users window
 - > Setup version 1.1.10
 - Client version = 1.1.1.0
 - Server version = 1.1.1.0
- Fixed bug time zones 20 to 24 in controller were not configuring properly
 - Setup version 1.1.9
 - O Client version = 1.1.0.0
 - Server version = 1.1.0.0
- New features in Operator:
 - Hide hardware items for operator
 - Disable control of items for operator
 - Hide columns in Events window for operator
- New design of Web reports page

- Fixed bug uncheck all readers in existing workgroup
- Fixed bug after portal name changed, old portal name is showing in events window
- Fixed bug on Client Startup on some PCs, Client can't connect to Server (blocking on Users table)(regional settings issue)
 - Setup version 1.1.8
 - Client version = 1.0.1.18
 - Server version = 1.0.1.20
- Fixed bug when changing serial number of controller
- Fixed bug with client cache on PCs with limited user permissions
 - > setup version 1.1.7
 - Client version = 1.0.1.17
 - Server version = 1.0.1.19
- Fixed bug with DST (Daylight Saving Time)
 - Setup version 1.1.6
 - o Client version = 1.0.1.16
 - Server version = 1.0.1.18
- Fixed bug with Scheduled Tasks
 - Setup version 1.1.5
 - Client version = 1.0.1.16
 - Server version = 1.0.1.17
- Fixed bug with Scheduled Tasks
- Fixed bug when Client is installed on a PC with different Time Zone than Server's PC Time Zone

- > Setup version 1.1.4
 - O Client version = 1.0.1.15
 - o Server version = 1.0.1.15
- Fixed bug with COM ports